



PC INDUSTRIES

176 AMBROGIO DRIVE, GURNEE, ILLINOIS 60031-3373 USA

Web Site: www.pcindustries.com E-Mail: sales@pcindustries.com
Phone (847) 336-3300 Fax (847) 336-3232

Guardian Offline Proofing System

Software User Manual

Document Reference:

Issue: Release

Revision: 4.03

Document Date: Jun. 2011

PC Industries

176 Ambrogio Drive, Gurnee, IL 60031 – USA

Tel. +1 847 336 3300 - Fax +1 847 336 3232

<http://www.pcindustries.com>

This Page Left Intentionally Blank.

Table of Contents

| | | |
|----------|---|----------|
| 1 | Introduction | 4 |
| 1.1 | Purpose and scope | 4 |
| 2 | Installation & Configuration | 5 |
| 2.1 | Hardware and Software Requirements | 5 |
| 2.2 | How to configure the application. | 5 |
| 2.3 | Cleaning the scanner glass. | 5 |
| 2.4 | Connect Scanner | 5 |
| 3 | USAGE..... | 6 |
| 3.1 | Introduction | 6 |
| 3.2 | Starting a New Project | 7 |
| 1. | New Project | 7 |
| 2. | Choose Master Image Type | 7 |
| 3. | Load Master Image | 7 |
| 4. | Scan Settings | 8 |
| 5. | Scan Master Image | 8 |
| 6. | Rotate Master Image | 8 |
| 7. | Region of Interest Box | 9 |
| 8. | Position Region of Interest Box | 9 |
| 9. | Add Mask Button | 10 |
| 10. | Position Locate Boxes | 10 |
| 11. | Train Master | 10 |
| 12. | Adjust Objects | 11 |
| 13. | Save Project | 12 |
| 14. | Master Image Window | 12 |
| 3.3 | Opening an Existing Project | 12 |
| 1. | Open Project | 12 |
| 2. | Select Project File | 13 |
| 3. | Choose Test Image Type | 13 |
| 4. | Load Test Image | 13 |
| 5. | Scan Test Image | 14 |
| 6. | Rotate Test Image | 14 |
| 7. | Auto-Find Number of Images | 15 |
| 8. | Show Advance Position Button | 15 |
| 9. | Enter Number of Images | 15 |
| 10. | Add Test Boxes | 15 |
| 11. | Adjust Test Box Spacing | 16 |
| 12. | Objects Background Selection buttons | 16 |

| | |
|---------------------------------------|----|
| 13. Perform Inspection | 16 |
| 14. Reset Button | 16 |
| 15. Save Project Button | 16 |
| 16. Overview Window | 17 |
| 17. Review Inspection Results..... | 18 |
| 3.4 Image Zoom Buttons | 21 |
| 1. Zoom In | 21 |
| 2. Zoom Out | 21 |
| 3. Zoom Fit | 21 |
| 3.5 Image Displayed Buttons | 21 |
| 1. Results - 1 | 21 |
| 2. Test - 2..... | 21 |
| 3. Master - 3..... | 21 |
| 3.6 System Settings | 22 |
| 1. Login Button | 22 |
| 2. Login Popup | 22 |
| 3. Sensitivity Settings | 23 |
| 4. Basic Settings..... | 24 |
| 5. Advanced Option Settings | 25 |
| 6. Advanced Object Settings..... | 26 |
| 7. Advanced Information Settings..... | 27 |

1 Introduction

1.1 Purpose and scope

The purpose of this document is to briefly describe the functionality of the Guardian Offline Proofing software.

1.2 Problem reporting instructions

Record any on-screen error messages, and details on what was done to help duplicate the problem and call PC Industries at 1-847-336-3300 for tech support.

2 Installation & Configuration

To install the Guardian Offline Proofing Software first uninstall (via control panel, add/remove program) previous versions of the Guardian Offline Proofing Software.

Insert installation disk into CD reader and click on setup.exe.

The setup program will then guide you through the rest of the procedure.

2.1 Hardware and Software Requirements

Microsoft Windows with Intel or AMD-based processor.

2.2 How to configure the application.

Configuration items are not handled in this version.

2.3 Cleaning the scanner glass.

1. Disconnect the power cord from the scanner.
2. Open the scanner lid.
3. Clean the glass using a soft lint-free cloth that has been moistened with glass cleaner.

2.4 Connect Scanner


1. Connect one end of the USB / Firewire cable to your computer, and connect the other end of the cable to the scanner's USB / Firewire port.
2. Press the Power button on the front panel of the scanner, and wait for the lights to stop blinking and stay on steady.

The scanner will be detected by your system automatically.

3 USAGE

3.1 Introduction

The Guardian Offline Proofing Software is developed by PC Industries to allow printers to automatically inspect and compare scanned printed images to a PDF or other scanned printed images. The software will also provide PDF to PDF comparison.




3.2 Starting a New Project

This section explains how to train a new master image.

1. New Project

Select the New button.

After you have selected the New button the Master Image buttons will be displayed.




2. Choose Master Image Type

The two choices are to Load Master from a file or Scan Master if there is a scanner attached to the computer. When scanning a master, you must select the desired DPI of the scan and either Color or Grayscale.

3. Load Master Image (Optional)

Click on the Load Master button (after selecting input type) at the top of the screen and the following dialog box will appear.



Select the type of file to load. The choices are TIF, BMP or PDF format. Select the file then press Open.

4. Scan Settings (Optional)

Click on the **Scan Master** button (after selecting input type) at the top of the screen and the following dialog box will appear.


The recommended setting is 600 **Scan DPI** (dots per inch) but 400 DPI can be used for faster speeds at a lower quality setting. There are also setting of 100 DPI and 200 DPI which can be used for large format images. The Master Image resolution should be at the selected dpi or higher. The software will automatically convert the resolution of the input file to match the selected resolution.

Scan Contrast and **Scan Brightness** settings are used to adjust the scan to match the master image quality. The **W"** width and **H"** height settings is provided in inches and can be set to match the sample size.

The **Test Box Mask** is used to mask the edges of the region of interest. This setting can be changed after the master setup is complete and the mask is displayed when toggling to the master image after the inspection is complete.

Resize Image is used to adjust test images to match master images when not input at 100% scaling.

Scanner Selection Box is used to indicate the type of Scanner. There are two selections, flatbed and large format.




5. Scan Master Image (Optional)

Click on the **Scan Master** button (after selecting input type) at the top of the screen and a dialog box from the scanner should appear indicating the scanner is acquiring the image.


6. Rotate Master Image

It's recommended that the master image match the orientation of the scanned images. The master image can't be rotated after it's trained but the scanned or test image can be rotated before inspecting. Click on **Rotate 90 CW** to rotate the image rotate 90 degrees clockwise, click on **Rotate 180** to rotate the image 180 degrees and click on **Rotate 90 CCW** to rotate the image 90 degrees counter-clockwise.



9. Add Mask Button

If you want to ignore a selected area of print, press Add Mask and size it accordingly. Click **Next Step** to proceed.




10. Position Locate Boxes

Left click the three Locate boxes and drag the boxes over areas of text or copy.

Locate Box General Rules:


- A. Place locate boxes over the same color print.
- B. Place the locate boxes as close to the corners as possible.
- C. Use unique features to avoid confusion.
- D. The lower locate box can be placed in either bottom corner.



Tip: Right click on the image to bring up the Zoom controls

11. Train Master

After positioning the locates, press the Train button to train Objects.



12. Adjust Objects (Optional)

After the software successfully trains, then Add or Delete any objects.



 A detailed label template for a "Dietary Supplement". On the left, a vertical banner reads "Guardian Inspection Systems™". The main content area includes:

- Directions:** Install an inspection system from PC Industries to improve quality, reduce waste, increase production and reduce liability. Do not ship defects to your customers.
- Important:** Proof-read all product information using the Guardian OLP off-line proofing system. This product compares print quality against a customer-supplied PDF.
- CAUTION:** Not for use by printers unconcerned about quality. The Guardian PQV provides true 100% inspection to ensure defect-free shipments.
- Supplement Facts:** Serving Size 1 Tablet, Servings Per Container 120.
- Amount Per Serving:** Inactive Ingredients 500 mg*.
- *Daily Value (DV) not established.**
- A list of 24 numerical values (e.g., .00125", .00250", .00375", .00500", .00625", .00750", .00875", .01000", .01125", .01250", .01375", .01500", .01625", .01750", .01875", .02000", .02125", .02250", .02375", .02500", .02625", .02750", .02875", .03000", .03125", .03250") each with a small square icon to its right.
- Fields for "Lot:" and "Exp:".
- PC Industries logo and website: www.pcindustries.com.
- A standard 1D barcode with the number 0 12345 67891 2 below it.
- A QR code.
- PN 105789 in the bottom right corner.


13. Save Project

The Master image must then be approved by pressing the **Save Project** button. After approving the Project Save As dialog will automatically appear prompting the project to be saved as a file name for future use. Enter a file name and click Save. The Guardian project files will be saved in the OLP format, which is a SQL Database file designed for the Guardian OLP.



14. Master Image Window

After saving the project the master image will be displayed in the upper left window. The open project name will also be displayed under the image. Right click to display zoom options.




3.3 Opening an Existing Project

This section will give you instructions on how to open an existing project and perform print quality inspection.


1. Open Project

Select the Open button to load an existing project.




2. Select Project File

A file open dialog box will appear. Select the .OLP file and click on the Open button.




3. Choose Test Image Type

The two choices are to Load Test from a file or Scan Test if there is a scanner attached to the computer.



4. Load Test Image (Optional)

Click on the **Load Test** button (after selecting input type) at the top of the screen and the following dialog box will appear.




Select the type of file to load. The choices are TIF, PDF and BMP. Select the file then press **Open**.

5. Scan Test Image (Optional)

Click on the Scan Test button at the top of the screen and a dialog box from the scanner should appear indicating the scanner is acquiring the image.

6. Rotate Test Image (Optional)

Click on Rotate 90 CW to rotate the image rotate 90 degrees clockwise, click on Rotate 180 to rotate the image 180 degrees and click on Rotate 90 CCW to rotate the image 90 degrees counter-clockwise.




7. Auto-Find Number of Images

Enter the number of images within the Scan for inspection and click the **Find** button. The software will automatically find and position as many test boxes as possible. **Skip to step 11 if all images are found and positioned correctly.**



Note: If images are displayed with blue "X" through them after clicking on the find button, then image scan was cut-off or the scanned image does not match the master image.



Only perform steps 8-12 if step 7 didn't successfully Auto Find all of the images


8. Show Advance Position Button

Click on the show Advance Position button to manually set the number of images.




9. Enter Number of Images (Optional)

Type in the number of images across into #Across and the number of images around into #Around. When this number is changed it will enable the Add Test Boxes button.



10. Add Test Boxes (Optional)

Click on the Add Test Boxes button after entering the number around and number across.



11. Adjust Test Box Spacing (Optional)

Click on the Test Box Spacing sliders or enter the spacing in pixels into the text boxes. While adjusting the sliders the test box spacing will adjust.

The 'Manual Positioning' dialog box contains several controls. On the left, there are two text boxes labeled '#Across' and '#Around', both containing the value '1'. To their right is a button labeled 'Add Boxes'. Further right are two vertical sliders, each with a text box above it containing the value '75'. These sliders and text boxes are enclosed in a red rectangular box. On the far right, there are three radio buttons: 'No Objects', 'Objects/Bkg' (which is selected), and 'Objects Only'.

12. Objects Background Selection buttons (Optional)

These selection buttons are used for selecting inspection parameters. It is possible to inspect objects only, background only, or objects and background. Objects and background is the default setting.

This image shows the same 'Manual Positioning' dialog box as in the previous section. In this view, the 'Objects/Bkg' radio button is selected. The 'No Objects' and 'Objects Only' buttons are also visible. These three radio buttons are enclosed in a red rectangular box.

13. Perform Inspection

Click on the Inspect button to perform inspection.

The 'Inspect' dialog box features a green header with the title 'Inspect'. Below the header, on the left, is a text box labeled '# 1'. To its right are five buttons: 'Find', 'Inspect', 'Reset', 'Save Project', and 'Show Adv. Pos.'. The 'Inspect' button is highlighted with a red rectangular box.

14. Reset Button

When the reset button is clicked the operator is allowed to reposition the region of interest boxes before conducting another inspection.

This image shows the 'Inspect' dialog box with the 'Reset' button highlighted by a red rectangular box. The other buttons and the '# 1' text box remain visible in their original positions.


15. Save Project Button

When the save project button is clicked the project is saved.


The 'Inspect' dialog box is shown with the 'Save Project' button highlighted by a red rectangular box. The other elements of the dialog box are unchanged.

16. Overview Window

Provides a window to display the current zoom area on the main window.



17. Review Inspection Results



#1 Test Box Location – Displays test box location relative to other boxes.

#2 Test Box Results – Displays defect score in pixels. If this number is larger than the defect limit the inspection failed due to defects.

#3 Defect Box – Displays blue defect boxes around defects that meet the defect size and contrast settings. Copy defects are displayed in red and background defects are displayed in yellow. If the mouse is hovered over the defect box the overall defect number and defect size is displayed.

#4 Zoom Menu – Right clicking inside image window will bring up the zoom settings menu.

#5 Defect Chart – Displays the result of the inspection. To move up through the defects click on the move up button or press the number 4 key on the keyboard. To reject a defect click on the reject button or press the number 5 key on the keyboard. To accept a defect click on the accept button or press the number 6 key on the keyboard. Click on the print screen button to print a picture of the screen and click on the PDF report button to Generate a secure PDF report for an inspection.

#6 PDF Report – Click on “Create Report” or “PDF Report”, depending on which report type was purchased with the system to display the detailed results of the inspection. The report is automatically saved to the hard drive and can be printed from directly from the on-screen report viewer.

Sample Report

Guardian OLP Certificate of Inspection

Result: Failed Inspection

Date: 6/28/2009

Time: 9:48:22 AM

Job Number:

Operator: john

Master File: RD1241_Color


Test File: RD1241_Color_Test1004281215.tif

Report File: RD1241_Color_090628094822C.pdf

Software Version: v2.36

Master Image

Test Image



Sensitivity Settings

Inspection Type = Objects/Background

DPI = 400

Min. Size Objects = 10

Min. Size Background = 10

Contrast Objects = 25

Contrast Background = 150

Register Objects = 2

Register Background = 20

Scan Width = 12

Scan Height = 17

Scan Contrast = 0

Scan Brightness = 0

Background Sensitivity = False

Enable False Defect Delete = False

Resize PerCent = 100

ROI Mask Type = Rectangle

Object Accept = 75

Object Border = 2

Object Search = 30

Object Edge Contrast = 30

Max Object Size = 500

Min Object Size = 4

Min Object Contrast = 30

Object Small Border = 3

Image Type = Color

Number Up = 9

Number Across = 1

Number Around = 1

Small Object Size = 15

Object Group Distance = 4

Object Ignore Inside = 1

Object Search Area = 150

Object Auto Contrast = 1

Background Objects = 0

Group Similar Objects = 1

Object Contrast Sensitivity = 0

Auto Find Accept = 30

X Scaling Enabled = 1

Y Scaling Enabled = 1

Max Defect Boxes = 500

Max Skew = 2.0

Skew Enabled = 1









Defect Boxes Enabled = 1

Highlight Enabled = 1

Group Defects = 1


Group Spacing = 75

Defects Found:4 Critical Defects:4

| Result | Defect Information | Defect Image | Master Image |
|--------|------------------------------|---|---|
| Reject | Defect:1 Row:4 Col:1 Size:15 |  |  |
| Reject | Defect:2 Row:4 Col:1 Size:32 |  |  |
| Reject | Defect:3 Row:4 Col:1 Size:18 |  |  |
| Reject | Defect:4 Row:4 Col:1 Size:26 |  |  |

3.4 Image Zoom Buttons

The image zoom buttons are used adjust the operators view of the image being inspected.



1. **Zoom In**
When zoom in is used the main viewing area displays an enlarged view of a specific portion of the image. The more zoomed in the smaller the portion of the main image being viewed.
2. **Zoom Out**
When zoom out is used the area being viewed becomes larger. Zoom out can will only work until the whole image is displayed in the main viewing area.
3. **Zoom Fit**
When zoom fit is used the main viewing area displays the complete image being inspected.

3.5 Image Displayed Buttons

These buttons allow the operator to cycle through an inspected image, the master image and a displayed image.




1. **Results - 1**
Clicking on this button or pressing the 1 button on the keyboard will display the inspection results.
2. **Test - 2**
Clicking on this button or pressing the 2 button on the keyboard will display the test image without the inspection results.
3. **Master - 3**
Clicking on this button or pressing the 3 button on the number keyboard will display the master image.

3.6 System Settings

This section gives instructions on how to adjust the sensitivity and system parameters. In order to change system and sensitivity setting it is necessary to log into the OLP system as a manager or administrator. There are three levels of security, operator, manager and administrator. Operators have no access to settings. Managers have access to sensitivity settings and basic settings. Administrators have access to all settings.

1. Login Button

Click on the Login Button to display the user login popup box.

A screenshot of a software interface. It features two text input fields at the top labeled 'Operator ID' and 'Job Number'. Below these fields is a 'Log In' button, which is highlighted with a red rectangular border. To the right of the 'Log In' button, the text 'Security Level Operator' is displayed.

2. Login Popup

In the Operator ID text box enter in a valid operator name. Next enter a valid password for the operator. Clicking on the OK button will log the operator into the system. Clicking on the cancel button will leave the system with the previous operators settings.

A screenshot of a 'Login' dialog box. The dialog has a title bar with the word 'Login' and standard window controls. Inside, there are two labels: 'Operator ID:' and 'Password:'. The 'Operator ID:' label is followed by a text box containing the text 'User Name'. The 'Password:' label is followed by a text box containing a series of asterisks. At the bottom of the dialog are two buttons: 'OK' and 'Cancel'.

3. Sensitivity Settings

Allows the sensitivity to be adjusted.

- a. **Min Defect Size – Objects/Background** – (in pixels) the software will filter and ignore defects blobs smaller than this setting. The lower the number increases the sensitivity to small defects.
- b. **Contrast – Objects / Background** – (in grayscale levels) the software will filter and ignore defects with a smaller contrast difference than this setting. The lower the number increases the sensitivity to light contrast defects.
- c. **Edges – Object / Background** – (in pixels) the software will filter and ignore defects on the edges of graphics or characters. The lower the number increases the sensitivity to register defects.

The screenshot shows a window titled "Sensitivity" with six sliders arranged in a 3x2 grid. Each slider has a numerical value displayed in a box to its left and a slider handle on a horizontal track. The settings are as follows:

| Setting | Value |
|---------------------|-------|
| Min Size Objects | 10 |
| Min Size Background | 25 |
| Contrast Objects | 130 |
| Contrast Background | 2 |
| Edges Objects | 2 |
| Edges Background | 10 |

4. Basic Settings

Allows the system performance to be adjusted.

a. Test Box Mask – Select the shape of the test box; there are three choices: Rectangular, Round Rectangular, and Ellipse.

b. Load / Save Settings – Allows the manager to load and save a set of default settings to be used for the current or a future project.

c. Object Settings (Manager Security Level)

1. Object Search – (in pixels) Area of locate box movement. The higher the number allows for coarser alignment of the test boxes at the expense of inspection processing time.

2. Object Accept – (percentage) Value required for a locate accept. The higher the value the more accurate, the lower the value the higher chance of locating incorrectly.

3. Object Search – (in pixels) Area of Object box movement. The higher the number allows for coarser alignment of the test boxes at the expense of inspection processing time.

4. Object Accept – (percentage) Value required for a locate accept. The higher the value the more accurate, the lower the value the higher chance of locating incorrectly.

5. Object Edge – (in grayscale) Used to detect the object edge contrast value on the master image. Set lower to detect lower contrast objects.

6. Max Object Size – (in pixels) Maximum size of an Object.

7. Auto Object Contrast – Un-check to manually control the Contrast setting for Objects.

8. High Object Sensitivity – Provides an alternate method of “Auto Object Contrast” which will tend to be more sensitive to contrast differences between the test image object and the master object.

9. High Bkgd Sensitivity – Provides an alternate method of “Auto Object Contrast” which will tend to be more sensitive to contrast differences between the test image object and the master object.

5. Advanced Option Settings

These settings used to adjust system performance, and are only accessible to the system administrator. When making changes to setting re-inspection is necessary for the changes to take effect.

- a. **Highlights** – When this option is enabled the OLP displays defect highlighting.
- b. **Defect Boxes** – When this option is enabled defect boxes are displayed around all image defects.
- c. **Group Defects** – When this option is enabled defects that are within the group defect spacing are grouped together.
- d. **Locate Boxes** – When this option is enabled locate boxes are displayed showing alignment issues for an inspected image.
- e. **Auto Find** – when this option is enabled the OLP will automatically find images from a loaded test file or scan.
- f. **Auto Inspect** – When this option is enabled the OLP will automatically inspect images from a test file or scan. Should be used in conjunction with Auto Find.
- g. **Auto Skew** – When this option is enabled the OLP will provide automatic skew adjustments.
- h. **X Autoscaling** – Allows automatic scaling along the horizontal axis.
- i. **Y Autoscaling** – Allows automatic scaling along the vertical axis.
- j. **Max Skew** – The maximum distance skew is allowed in Degrees.
- k. **Find Accept** – The minimum acceptable match percent for Find.
- l. **Max Defects** – The maximum number of ant type of defect allowed in an Inspection. The OLP will provide a message if this limit is exceeded.
- m. **Update Rate** – This setting is the number of inspections plus one that will happen before a screen is updated.
- n. **Group Spacing** – Distance in pixels defects must be within for grouping defect boxes.
- o. **Locate Search** – is used for adjusting the size for the locate search area (in pixels) on a test image. Decreasing this number improves the maximum inspection speed. Increase this number if inspections fail due to acceptable positional variations on the test image.
- p. **Locate Accept** – sets the minimum match value for the locate image acceptance. Decrease this number if the inspection fails because of acceptable quality variations on the test image. Increase this number to fail unacceptable quality variations on the test image and to prevent incorrectly locating on similar areas of print. Typical setting: 50 to 85.

| Options | | Objects | Info |
|---|---|---|-------------------|
| <input checked="" type="checkbox"/> Highlight | <input type="checkbox"/> Auto Find | <input checked="" type="checkbox"/> X Autoscaling | 500 Max Defects |
| <input checked="" type="checkbox"/> Defect Boxes | <input type="checkbox"/> Auto Inspect | <input checked="" type="checkbox"/> Y Autoscaling | 2 Update Rate |
| <input checked="" type="checkbox"/> Group Defects | <input checked="" type="checkbox"/> Auto Skew | 30 Find Accept | 75 Group Spacing |
| <input type="checkbox"/> Locate Boxes | 2 Max Skew | 50 Locate Accept | 150 Locate Search |

6. Advanced Object Settings

These settings are used to define objects, and are only accessible to the system administrator. When making changes to settings, re-inspection is necessary for the changes to take effect.

- a. **Object Min** – Filters objects found below this total pixel size during object training. Decrease this number to allow for smaller objects to be trained and inspected. Increase this number to reduce the number of small objects trained. Typical setting: 4 to 10.
- b. **Object Border** – Sets the border area around found objects during object training. Decrease this number to separate and inspect more objects independently. Increase this number to enlarge the area around the object to be inspected at the object sensitivity level. Typical setting: 0 to 3.
- c. **Min Contrast** – is used to filter out low contrast objects. A low minimum contrast will allow for recognition of a higher volume of objects, while a high minimum contrast will recognize fewer objects.
- d. **Group Distance** – The distance in pixels objects will be grouped as a single object.
- e. **Small Border** – This is the size of the border placed around small objects in pixels.
- f. **Small Object Size** – Objects with widths or heights less than this setting in pixels will have the small object border placed around them.
- g. **Smooth Master** – When checked applies a smoothing algorithm to smooth edges for improved object training.
- h. **Group Objects** – When enabled allows for the grouping of objects within the group distance.
- i. **Ignore Inside** – Removes objects trained inside other objects.
- j. **Objects** – This displays the total number of objects found in an inspection.
- k. **Display Objects** – This displays the object locations on the master image for the last region inspected.
- l. **Repeat Train** – Retrains the objects during the inspection process for all regions.
- m. **Pos Diff Check** – Algorithm that limits the search area and locates for objects.

| Options | Objects | Info |
|---|---|---|
| <input type="text" value="2"/> Object Min | <input type="text" value="3"/> Small Border | <input checked="" type="checkbox"/> Display Objects |
| <input type="text" value="2"/> Object Border | <input type="text" value="15"/> Small Object Size | <input type="checkbox"/> Repeat Train |
| <input type="text" value="30"/> Min Contrast | <input checked="" type="checkbox"/> Group Objects | <input checked="" type="checkbox"/> Smooth Master |
| <input type="text" value="1"/> Group Distance | <input checked="" type="checkbox"/> Ignore Inside | <input type="checkbox"/> Pos Diff Check |

